

## Unit 20 – Session 2

Last time, we looked at two separate concepts:

- Field lines
  - # of lines is directly proportional to the magnitude of the charge.
- Flux,  $\Phi \equiv \vec{E} \cdot \vec{A} = |\vec{E}| |\vec{A}| \cos \theta$ 
  - Flux is directly proportional to the # of lines at the surface of an area, pointing outward (positive flux) or pointing inward (negative flux).

When we introduced the concept of work,  $W \equiv \vec{F} \cdot \Delta \vec{s} = |\vec{F}| |\Delta \vec{s}| \cos \phi$ , last semester, it wasn't that useful to us until we related it to another concept: change in kinetic energy,  $\Delta K \equiv \frac{1}{2}mv_2^2 - \frac{1}{2}mv_1^2$ .

- $W = \Delta K$       or       $|\vec{F}| |\Delta \vec{s}| \cos \phi = \frac{1}{2}mv_2^2 - \frac{1}{2}mv_1^2$

## Activity 20.5

Here, we are going to combine the concepts of field lines and flux together to get a useful relationship, like we did for work and kinetic energy.

Our previous exploration of flux was for an **open** surface (a sheet of paper) – however, the concept of flux won't be useful to us unless we look at a 3-dimensional **closed** surface, with a volume inside our surface (like a sphere, or a box, or a cylinder).

Some terms and “rules”:


- 1) You can pick any surface area shape you want, but it must be a **closed** surface area (encloses a volume).
- 2) The surface area is called a **Gaussian surface**
- 3) The unit area vectors of the surface always point **outward**.
- 4)  $\vec{E}$  field lines pointing from inside to outside  $\Rightarrow +\Phi^{elec}$   
 $\vec{E}$  field lines pointing from outside to inside  $\Rightarrow -\Phi^{elec}$


Since 3-dimensional surfaces are hard to draw on paper, we will explore the relationship between electric field lines and flux using an abstract world called Flatland:


Instead of a closed surface area surrounding a volume


⇒ a closed boundary line surrounding an area.


An example (before we do Activity 20.5.1).



















## Activity 20.5.2.

Hopefully, you concluded a few things from your observations:

- The flux at the boundary of a **closed** surface is directly proportional to the total amount of charge enclosed by that surface:

- $\Rightarrow \Phi^{elec} = (\text{constant})q^{enclosed}$

- We aren't doing the 3<sup>rd</sup> session for this Unit (20.8 & 20.9) – we would find there that the *constant* is equal to  $4\pi k$ , where  $k$  is Coulomb's constant. It is sometimes written instead as  $constant = 4\pi k = \frac{1}{\epsilon_0}$  ( $\epsilon_0$  is pronounced “epsilon zero” or “epsilon naught”).

- This relationship between the net flux at the boundary of a closed surface and the enclosed charge is called **Gauss' Law**.

$$|\vec{E}| |\vec{A}| \cos \theta = 4\pi k q^{enclosed}$$


- $\Rightarrow |\vec{E}| |\vec{A}| \cos \theta = \frac{q^{enc}}{\epsilon_0}$

## Activity 20.5.2 (continued)

There are a couple of things to note about Gauss' Law

- If you know or are given the total amount of charge inside the closed surface, the right side of the equation ( $4\pi kq^{enc}$ ) is easy to calculate.
- The left side of the equation is not easy to calculate unless we limit ourselves to a few special cases:
  - The magnitude of the electric field ( $|\vec{E}|$ ) is the same everywhere on the closed surface.
  - The angle ( $\theta$ ) between the electric field vector ( $\vec{E}$ ) and the area vector ( $\vec{A}$ ) is always the same everywhere on the closed surface.

$|\vec{E}||\vec{A}|\cos\theta$  is easy to calculate.



$|\vec{E}||\vec{A}|\cos\theta$  is not easy to calculate.

